

ZX0010 - Message Code Table

Required table. Codes defined by SBCTC-ITD.

Use the Message Code Table to create the messages that are displayed in FMS, PPMS and SMS. The message information includes the message number, text and severity.

For a complete list of message codes, run the DataExpress procedure ZX0010R (from Group Inform, Account PLIB).

User Function Keys

Protected Functions	
F2	ADD
F3	CHANGE, except as noted below
User Functions	
F1	REFRESH
F3	CHANGE Message Severity (if CHANGE IND is Y), Status and Message Text
F4	INQUIRY
F8	MENU

Data Fields

MESSAGE CODE PRG (key field)	CHANGE IND (display only)
MESSAGE CODE NUM (key field)	MESSAGE CODE STATUS (required)
RVSN DATE (display only)	MESSAGE TEXT
MESSAGE SEVERITY (display only unless Change Indicator is set to Y)	

Message Code Program (MC-MSG-PRG)

Description	Key field. A code identifying the program number associated with each message, for example, GA1093.
Length	6 characters

Message Code Number (MC-MSG-NUM)

Description	Key field. The number assigned to each message in a program, for example, 0001.
Length	4 characters

Revision Date (RVSN-DATE)

Description	Display only. A date assigned by the system indicating when the current record was changed or added.
--------------------	--

Message Severity (MSG-SEVERITY)

Description	Display only, unless Change Ind is set to Y (yes). A code identifying the severity
--------------------	--

	of the message.
Length	1 digit
Values	Defined by SBCTC-ITD as follows: 0 Suppress print (not displayed) 1 Informational (displayed online, for example, ADD COMPLETE) 2 Warning (update to data processed; message appears on daily reports) 3 Serious (update to data processed; message appears on daily reports) 4 Fatal (update to data not processed) 5 System error (contact the data processing center or your system manager)
Edit	Cannot be left blank

Change Indicator (CHNG-IND)

Description	Display only. A code indicating whether the Message Severity field can be changed by a user. This field cannot be left blank.
Length	1 character
Values	Defined by SBCTC-ITD as follows: Y Yes, the severity of the message can be changed N No, the severity of the message cannot be changed

Message Code Status (EDIT-STAT)

Description	Entry required. A code identifying the status of the key field.
Length	1 character
Values	Defined by SBCTC-ITD as follows: A Active (default) L Limited I Inactive D Delete Note: Do not change the Message Code State field unless authorized by the data processing center or your system manager.

Message Text

Description	The text of the message.
Length	58 characters

Data Sets

Additions and changes made on this screen may update the following data sets:

- Error Code Table (MSG-TBL-M)